List of Keys (Keyboard, Mouse and Joystick)

Mouse

General Buttons

LButton Left mouse button
RButton Right mouse button

MButton Middle or wheel mouse button

Advanced Buttons

XButton1 4th mouse button. Typically performs the same function as

Browser_Back.

XButton2 5th mouse button. Typically performs the same function as

Browser_Forward.

Wheel

WheelDown Turn the wheel downward (toward you).
WheelUp Turn the wheel upward (away from you).

[v1.0.48+]: Scroll to the left or right.

Requires Windows Vista or later. These can be used as hotkeys WheelLeft with some (but not all) mice which have a second wheel or

WheelRight support tilting the wheel to either side. In some cases, software bundled with the mouse must instead be used to control this feature. Regardless of the particular mouse, <u>Send</u> and <u>Click</u> can

be used to scroll horizontally in programs which support it.

Keyboard

Note: The names of the letter and number keys are the same as that single letter or digit. For example: b is the B key and 5 is the 5 key.

Although any single character can be used as a key name, its meaning (scan code or virtual keycode) depends on the current keyboard layout. Additionally, some special characters may need to be escaped or enclosed in braces, depending on the context. [v1.1.27+]: The letters a-z or A-Z can be used to refer to the corresponding virtual keycodes (usually vk41-vk5A) even if they are not included in the current keyboard layout.

General Keys

CapsLock (caps lock key)

Space Space (space bar)
Tab Tab (tabulator key)

Enter (or Return) Enter Escape (or Esc) Esc

Backspace (or BS)

Backspace

Cursor Control Keys

ScrollLock ScrollLock (scroll lock key)

Delete (or Del)

Insert (or Ins)

Home

End

Delete

Home

End

PgUp PageUp (page up key)

PgDn PageDown (page down key)

Numpad Keys

Due to system behavior, the following keys seperated by a slash are identified differently depending on whether NumLock is ON or OFF. If NumLock is OFF but Shift is pressed, the system temporarily releases Shift and acts as though NumLock is ON.

Numpad3 / NumpadPgDn 3 / PageDown

 $Numpad4 / NumpadLeft \qquad 4 / \leftarrow$

Numpad5 / NumpadClear 5 / typically does nothing

 $\begin{tabular}{lll} Numpad6 / NumpadRight & 6 / \rightarrow \\ Numpad7 / NumpadHome & 7 / Home \\ Numpad8 / NumpadUp & 8 / ↑ \end{tabular}$

 $\begin{aligned} & Numpad9 \ / \ NumpadPgUp & 9 \ / \ \texttt{PageUp} \\ & NumpadDot \ / \ NumpadDel & . \ / \ \texttt{Delete} \end{aligned}$

NumLock NumLock (number lock key)

NumpadDiv / (division)

NumpadMult * (multiplication)

NumpadAdd + (addition)

NumpadSub - (subtraction)

NumpadEnter Enter

Function Keys

F1 - F24 The 12 or more function keys at the top of most keyboards.

Modifier Keys

LWin Left win. Corresponds to the <# hotkey prefix.

Right Win. Corresponds to the ># hotkey prefix.

RWin Note: Unlike Control/Alt/Shift, there is no generic/neutral

"Win" key because the OS does not support it. However, hotkeys with the # modifier can be triggered by either Win key.

Control (or Ctrl)

Control (or Ctrl)

Control (or Ctrl)

Control (or Ctrl)

it has the tilde prefix. Corresponds to the ^ hotkey prefix.

Alt. As a hotkey (Alt::) it fires upon release unless it has the

tilde prefix. Corresponds to the! hotkey prefix.

Shift. As a hotkey (Shift::) it fires upon release unless it has

the tilde prefix. Corresponds to the + hotkey prefix.

LControl (or LCtrl)

RControl (or RCtrl)

Left control. Corresponds to the <^ hotkey prefix.

Right control. Corresponds to the >^ hotkey prefix.

LShift

Left Shift. Corresponds to the <+ hotkey prefix.

RShift Right Shift. Corresponds to the >+ hotkey prefix.

Left Shift. Corresponds to the >+ hotkey prefix.

Left Alt. Corresponds to the <! hotkey prefix.

Right Alt. Corresponds to the >! hotkey prefix.

RAlt Note: If your keyboard layout has AltGr instead of RAlt, you

can probably use it as a hotkey prefix via <^>! as described here. In addition, LControl & RAlt:: would make AltGr

itself into a hotkey.

Multimedia Keys

The function assigned to each of the keys listed below can be overridden by modifying the Windows registry. This table shows the default function of each key on most versions of Windows.

Browser_Back Back
Browser_Forward Forward
Browser_Refresh Refresh
Browser_Stop Stop
Browser_Search Search

Browser_Favorites Favorites
Browser_Home Homepage

Volume_Mute Mute the volume
Volume_Down Lower the volume
Volume_Up Increase the volume

Media_Next Next Track
Media_Prev Previous Track

Media_Stop Stop

Media_Play_Pause Play/Pause

Launch_Mail Launch default e-mail program
Launch_Media Launch default media player
Launch_App1 Launch My Computer

Launch_App2 Launch Calculator

Other Keys

AppsKey Menu. This is the key that invokes the right-click context menu.

PrintScreen PrintScreen CtrlBreak Ctrl+Break

Pause Pause

Break Break Since this is synonymous with Pause, use ^CtrlBreak

in hotkeys instead of ^Pause or ^Break.

Help. This probably doesn't exist on most keyboards. It's

usually not the same as F1.

Sleep. Note that the sleep key on some keyboards might not

work with this.

SCnnn Specify for nnn the scan code of a key. Recognizes unusual

keys not mentioned above. See Special Keys for details.

Specify for **nn** the hexadecimal virtual key code of a key. This rarely-used method also prevents certain types of <u>hotkeys</u> from requiring the <u>keyboard hook</u>. For example, the following hotkey does not use the keyboard hook, but as a side-effect it is

triggered by pressing either Home or NumpadHome:

 $^{\text{VK24}::\underline{\text{MsgBox}}}$ You pressed Home or NumpadHome while holding down Control.

Sι

VKnn

Known limitation: VK hotkeys that are forced to use the <u>keyboard hook</u>, such as *VK24 or ~VK24, will fire for only one of the keys, not both (e.g. NumpadHome but not Home). For more information about the VKnn method, see <u>Special Keys</u>.

Warning: Only <u>Send</u>, <u>GetKeyName</u>, <u>GetKeyVK</u>, <u>GetKeySC</u> and <u>#MenuMaskKey</u> support combining VKnn and SCnnn.

[v1.1.27+]: The presence of an invalid suffix prevents VKnn from being recognized. For example, vk1Bsc001: raises an error in v1.1.27+, but sc001 was ignored (had no effect) in previous versions.

Joystick

Joy1 through Joy32: The buttons of the joystick. To help determine the button numbers for your joystick, use this <u>test script</u>. Note that <u>hotkey prefix symbols</u> such as ^ (control) and + (shift) are not supported (though <u>GetKeyState</u> can be used as a substitute). Also note that the pressing of joystick buttons always "passes through" to the active window if that window is designed to detect the pressing of joystick buttons.

Although the following Joystick control names cannot be used as hotkeys, they can be used with GetKeyState:

JoyX, **JoyY**, and **JoyZ**: The X (horizontal), Y (vertical), and Z (altitude/depth) axes of the joystick.

JoyR: The rudder or 4th axis of the joystick.

JoyU and **JoyV**: The 5th and 6th axes of the joystick.

JoyPOV: The point-of-view (hat) control.

JoyName: The name of the joystick or its driver.

JoyButtons: The number of buttons supported by the joystick (not always accurate).

JoyAxes: The number of axes supported by the joystick.

JoyInfo: Provides a string consisting of zero or more of the following letters to indicate the joystick's capabilities: **Z** (has Z axis), **R** (has R axis), **U** (has U axis), **V** (has V axis), **P** (has POV control), **D** (the POV control has a limited number of discrete/distinct settings), **C** (the POV control is continuous/fine). Example string: ZRUVPD

Multiple Joysticks: If the computer has more than one joystick and you want to use one beyond the first, include the joystick number (max 16) in front of the control name. For example, 2joy1 is the second joystick's first button.

Note: If you have trouble getting a script to recognize your joystick, one person reported needing to specify a joystick number other than 1 even though only a single joystick was present. It is unclear how this situation arises or whether it is normal, but experimenting with the joystick number in the joystick test script can help determine if this applies to your system.